

# MTS/T-BERD 6000A V2 B19163 RELEASE NOTE

# Ste-Core Package 19163 (April 2019)

-	Boot	V9.04	11/April/2019
-	Linux Kernel	V8.82	16/April/2019
-	File System	V8.02	11/April/2019

# Ste-Optical Package 19163 (April 2019)

-	Instrument Setup	V18.00	17/April/2019
-	Microscope	V18.00	17/April/2019
-	Fiber Optics	V18.00	17/April/2019



# **CONTENTS**

CONTENTS	2
T-BERD/MTS 6000AV2 Base Unit	
New functionalities	
Improvements	3
OTDR	3
New functionalities	3
Improvements	3
FiberComplete	
Improvements	3
PMD/In-band PMD/CD	3
Improvements	3
Scope	3
New functionalities	3
Improvements	3



# T-BERD/MTS 6000AV2 Base Unit

#### New functionalities

- > New file manager user interface
- New handling of demo licences

#### *Improvements*

- > Now, direct possible access to EU StrataSync server link
- > In case of SAA use with wifi, the wifi autoconnect is always activated
- > Improved handling of auto IP via Ethernet cable
- > Improved handling of auto wifi connect in AP master mode
- > Improved management of wifi ad-hoc mode
- > Improved cursor positioning on the keyboard (now last position instead of always first character before)
- > Improved keyboard for wifi password (more characters are available)
- > Improved management of file exchange via bluetooth or email
- > Improved management of file manager with many files
- > Improved management of SAA with wifi when the ethernet is set to a given predefined config without connection to an Ethernet cable
- > Improved upgrade menu when performing an upgrade from the boot menu

# **OTDR**

#### New functionalities

> New SmartTest user interface

#### **Improvements**

- > Correction of issue when moving from Expert SM OTDR to Expert MM OTDR function
- > Improved automatic measurements on short distance as well as on PON configurations
- > Improved automatic distance measurement of close reflective events
- > Expension table arrow no longer active in Smartlink view, only in trace view
- > Improved txt link manager file export access
- > Improved handling of cursors on PDF reports, when launch cables are used

# FiberComplete

### *Improvements*

- > Improved management of link manager with cable view of FiberComplete
- > Capability to perform bidirectional insertion loss only, without bidirectional ORL, on FiberComplete version 2
- > Improved handling of fiber increment between units, this after manual storage

## PMD/In-band PMD/CD

# *Improvements*

- Addition of pass/fail settings on the PMD and CD reports
- > improvemed management of renaming a .PIB file

#### Scope

#### New functionalities

> Addition of the increment value on the microscope function

#### **Improvements**

- > Improved management of microscope image, when the connector is not well centered
- > Improved handling of microscope profiles at power down (remains at the next power up)
- > Improved handling of the date format on the PDF report